

FusionPBX

Configuration Sip Trunk

1. Dans Accounts > Gateways: rajouter un compte

Gateway

Defines a connections to a SIP Provider or another SIP server.

Gateway	<input type="text" value="OVH"/> <small>Enter the gateway name here.</small>
Username	<input type="text" value="0032"/> <small>Enter the username here.</small>
Password	<input type="password" value="....."/> <small>Enter the password here.</small>
From User	<input type="text"/> <small>Enter the from-user here.</small>
From Domain	<input type="text"/> <small>Enter the from-domain here.</small>
Proxy	<input type="text" value="sip5.ovh.be"/> <small>Enter the hostname or IP address of the proxy. host[:port]</small>
Realm	<input type="text" value="sip5.ovh.be"/> <small>Enter the realm here.</small>
Expire Seconds	<input type="text" value="1800"/> <small>Enter the expire-seconds here.</small>
Register	<input checked="" type="checkbox" value="True"/> <small>Choose whether to register.</small>
Retry Seconds	<input type="text" value="30"/> <small>Enter the retry-seconds here.</small>
⚙️ ADVANCED	
Context	<input type="text" value="public"/> <small>Enter the context here.</small>
Profile	<input type="text" value="external"/> <small>Enter the profile here.</small>

2. Dans Advanced > Access control: rajouter l'IP Wan du serveur SIP Trunk dans la règle Providers

Access Control

Access control list can allow or deny ranges of IP addresses.

Name	<input type="text" value="providers"/>	Enter the name.												
Default	<input type="button" value="deny"/>	Select the default type.												
Nodes	<table border="1"><thead><tr><th>Type</th><th>CIDR</th><th>Description</th><th>Action</th></tr></thead><tbody><tr><td><input type="button" value="allow"/></td><td><input type="text" value="91.121.129.133/32"/></td><td><input type="text" value="OVH"/></td><td><input type="checkbox"/></td></tr><tr><td><input type="button" value=""/></td><td><input type="text" value=""/></td><td><input type="text" value=""/></td><td><input type="checkbox"/></td></tr></tbody></table>	Type	CIDR	Description	Action	<input type="button" value="allow"/>	<input type="text" value="91.121.129.133/32"/>	<input type="text" value="OVH"/>	<input type="checkbox"/>	<input type="button" value=""/>	<input type="text" value=""/>	<input type="text" value=""/>	<input type="checkbox"/>	Enter the description.
Type	CIDR	Description	Action											
<input type="button" value="allow"/>	<input type="text" value="91.121.129.133/32"/>	<input type="text" value="OVH"/>	<input type="checkbox"/>											
<input type="button" value=""/>	<input type="text" value=""/>	<input type="text" value=""/>	<input type="checkbox"/>											
Description	<input type="text"/>	Enter the description												

3. Dans Status > Sip Status: Relancer les ACL

4. Dans Dialplan > Destination: Ajouter une règle pour le numéro entrant

Destination

Inbound destinations are the DID/DDI, DNIS or Alias for inbound calls.

Type	<input type="button" value="Inbound"/>	Select the type.
Country Code	<input type="text"/>	Enter the country code.
Destination	<input type="text" value="003:"/>	Enter the destination.
Caller ID Name	<input type="text"/>	Enter the caller ID name.
Caller ID Number	<input type="text"/>	Enter the caller ID number.
Context	<input type="text" value="public"/>	Enter the context.
Conditions	<input type="text"/> <input type="text"/>	If the condition matches perform the action.
Actions	<input type="button" value="3000 AppelEntrant"/> <input type="button" value=""/>	Add additional actions.
User	<input type="text"/>	Assign this destination to a user.

Autoprovision


Snom

1. Dans l'interface du téléphone, choisir Advanced, QOS/Security et introduire le "http client" user et password qui correspond au http_auth_username et http_auth_password que vous avez défini

dans les default settings de Fusion Pbx


The screenshot shows the FusionPBX configuration interface. On the left is a navigation menu with sections: **Operation** (Home, Directory), **Setup** (Preferences, Speed Dial, Function Keys, Identity 1-12, Action URI Settings, **Advanced**, Certificates, Software Update), and **Status** (System Information, Log, SIP Trace, DNS Cache, Subscriptions, PCAP Trace, Memory, Settings, Manual). The main content area has tabs: Network, Behavior, Audio, SIP/RTP, **QoS/Security**, and Update. The **QoS/Security** tab is active and contains sections: **Quality of Service** (RTP and SIP Type of Service), **VLAN** (VLAN Id and Priority), **PC Port** (VLAN Id and Priority), **IEEE 802.1X Authentication:** (Off, User, Password), **Security** (Ignore Security Advises, Use Hidden Tags, Restrict URI Queries, Allow CSTA Control, Empty Client Cert, Filter Packets from Registrar, Authentication for SIP Reboot/Check-Sync, Administrator Mode, Administrator Password/Confirmation, Minimum PIN Length, Maximum PIN Retries), **HTTP Server** (User: admin, Password, Authentication Scheme: Digest), and **HTTP Client** (User: phone_mgmt, Password). Red boxes and circles with numbers 1, 2, and 3 highlight the 'Advanced' menu item, the 'QoS/Security' tab, and the 'HTTP Client' fields respectively.

2. Ensuite dans l'onglet Update, introduire l'url de provisioning exemple <http://192.168.103.30/app/provision/index.php?mac={mac}> et faire Apply



3. Après un redémarrage, un problème de certificat apparaîtra. Cliquez dans le menu certificates → unknown certificates et acceptez l'exception

Certificates



Debugging

sngrep

sngrep est livré par défaut et permet de voir chaque trace d'une transaction SIP

sngrep - SIP messages flow viewer

Current Mode: **Online [any]** Dialogs: 59
 Match Expression: BPF Filter:
 Display Filter:

Idx	Method	SIP From	SIP To	Msgs	Source	Destination	Call State
[] 1	OPTIONS	keepalive@91.121.129.133	003271115926@sip5.ovh.be	2	91.121.129.133:5060	192.168.103.30:5080	
[] 2	REGISTER	400@192.168.103.30:5060	400@192.168.103.30:5060	4	192.168.103.150:5060	192.168.103.30:5060	
[] 3	REGISTER	400@192.168.103.30:5060	400@192.168.103.30:5060	4	192.168.103.150:5060	192.168.103.30:5060	
[] 4	INVITE	0032467767338@sip5.ovh.be	003271420647@10.7.1.163	8	91.121.129.133:5060	192.168.103.30:5080	CANCELLED
[] 5	INVITE	0032467767338@192.168.103	301@192.168.103.101:5060	7	192.168.103.30:5060	192.168.103.101:5060	CANCELLED
[] 6	OPTIONS	keepalive@91.121.129.133	003271115926@sip5.ovh.be	2	91.121.129.133:5060	192.168.103.30:5080	
[] 7	INVITE	0032467767338@192.168.103	302@192.168.103.101:5060	7	192.168.103.30:5060	192.168.103.101:5060	CANCELLED
[] 8	OPTIONS	keepalive@91.121.129.133	003271115926@sip5.ovh.be	2	91.121.129.133:5060	192.168.103.30:5080	
[] 9	OPTIONS	keepalive@91.121.129.133	003271115926@sip5.ovh.be	2	91.121.129.133:5060	192.168.103.30:5080	
[] 10	OPTIONS	keepalive@91.121.129.133	003271115926@sip5.ovh.be	2	91.121.129.133:5060	192.168.103.30:5080	
[] 11	INVITE	0032495863286@sip5.ovh.be	003271420647@10.7.1.163	8	91.121.129.133:5060	192.168.103.30:5080	COMPLETED
[] 12	INVITE	0032495863286@192.168.103	301@192.168.103.101:5060	7	192.168.103.30:5060	192.168.103.101:5060	CANCELLED
[] 13	INVITE	0032495863286@192.168.103	302@192.168.103.101:5060	9	192.168.103.30:5060	192.168.103.101:5060	COMPLETED
[] 14	OPTIONS	keepalive@91.121.129.133	003271115926@sip5.ovh.be	2	91.121.129.133:5060	192.168.103.30:5080	
[] 15	OPTIONS	keepalive@91.121.129.133	003271115926@sip5.ovh.be	2	91.121.129.133:5060	192.168.103.30:5080	
[] 16	INVITE	400@192.168.103.30	300@192.168.103.30:5060	10	192.168.103.150:5060	192.168.103.30:5060	COMPLETED
[] 17	OPTIONS	keepalive@91.121.129.133	003271115926@sip5.ovh.be	2	91.121.129.133:5060	192.168.103.30:5080	
[] 18	OPTIONS	keepalive@91.121.129.133	003271115926@sip5.ovh.be	2	91.121.129.133:5060	192.168.103.30:5080	
[] 19	REGISTER	400@192.168.103.30:5060	400@192.168.103.30:5060	12	192.168.103.150:5060	192.168.103.30:5060	
[] 20	REGISTER	400@192.168.103.30:5060	400@192.168.103.30:5060	8	192.168.103.150:5060	192.168.103.30:5060	
[] 21	REGISTER	400@192.168.103.30:5060	400@192.168.103.30:5060	8	192.168.103.150:5060	192.168.103.30:5060	

From:
<https://wiki.makeitsimple.be/> - makeITsimple wiki

Permanent link:
<https://wiki.makeitsimple.be/doku.php?id=linux:fusionpbx&rev=1717145283>

Last update: **2024/05/31 08:48**

